


# ArcGIS® StreetMap™ Premium Custom Roads—ArcGIS Pro 3.3

December 2025



THE SCIENCE OF WHERE®

380 New York Street  
Redlands, California 92373-8100 USA

909 793 2853  
info@esri.com

esri.com

Copyright © 2025 Esri  
All rights reserved.  
Printed in the United States of America.

The information contained in this document is the exclusive property of Esri. This work is protected under United States copyright law and other international copyright treaties and conventions. No part of this work may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording, or by any information storage or retrieval system, except as expressly permitted in writing by Esri. All requests should be sent to Attention: Contracts and Legal Services Manager, Esri, 380 New York Street, Redlands, CA 92373-8100 USA.

The information contained in this document is subject to change without notice.

Esri, the Esri globe logo, The Science of Where, StreetMap, ArcGIS, [esri.com](http://esri.com), and @esri.com are trademarks, service marks, or registered marks of Esri in the United States, the European Community, or certain other jurisdictions. Other companies and products or services mentioned herein may be trademarks, service marks, or registered marks of their respective mark owners.

## Table of Contents

<b>Introduction to ArcGIS StreetMap Premium Custom Roads.....</b>	<b>1</b>
Technical restrictions .....	1
Licensing requirements .....	2
<b>Layer descriptions.....</b>	<b>4</b>
Custom_Streets .....	4
Custom_Streets_Override.....	4
Custom_Turns .....	5
<b>Editing templates .....</b>	<b>5</b>
Custom Streets .....	6
Custom Streets Override .....	6
Managing Editing Templates .....	6
<b>Loading Pre-existing Street Segments .....</b>	<b>7</b>
<b>Tasks.....</b>	<b>7</b>
Merge existing street data into StreetMap Premium network dataset.....	8
Task 1: Assess your street data.....	9
Task 2: Prepare your street data for merging .....	9
Task 3: Remove duplicate road segments .....	10
Task 4: Identify and fix remaining geometry issues .....	10
Task 5: Append your streets to Custom_Streets .....	10
Task 6: Connect Custom_Streets to Routing_Streets .....	10
Task 7: Set up turns .....	10
Task 8: Build your network dataset.....	10
Task 9: Verify network connectivity .....	11
Task 10: Create and share a mobile map package .....	11
Convert file geodatabase to uncompressed mobile file geodatabase.....	11
<b>Update process .....</b>	<b>12</b>

<b>Reference documents.....</b>	<b>13</b>
<b>Support .....</b>	<b>13</b>
<b>Data dictionary.....</b>	<b>14</b>
Point layers .....	14
Custom Streets Override Points (Custom_Streets_Override) .....	14
Line layers.....	14
Custom Streets for network (Custom_Streets) .....	14
Custom Turn Restrictions (Custom_Turns) .....	30
<b>Reference.....</b>	<b>42</b>
Directional Identifiers.....	42
Direction on Sign.....	43
Hierarchy .....	43
Maneuver Class Codes .....	44
Road Classes .....	44
Speed Categories .....	45
Speed Classes.....	45
Contents .....	46

# Introduction to ArcGIS StreetMap Premium Custom Roads

ArcGIS StreetMap Premium Custom Roads allows organizations to combine roads that they manage with StreetMap Premium streets for a single continuous routable transportation network.

ArcGIS StreetMap Premium provides ready-to-use geocoding, routing, and map display content for use within ArcGIS Pro and ArcGIS Enterprise, behind your firewall on infrastructure that you manage. The Custom Roads dataset includes a vector tile package (.vtpk) and a network dataset in a file geodatabase (.gdb), as well as separate locator files for geocoding.

The .vtpk file is the same as the Esri Navigation map that includes the commercial data, plus other GIS user community contributions. The map 'Navigation Map with Custom Streets (vtpk)' is the default map in ArcGIS Pro for creating your own mobile map packages. In addition, the product offers the ArcGIS StreetMap Premium locators. To [use the locators](#), as well as the network dataset, the ArcGIS StreetMap Premium extension for your region is required for ArcGIS Pro or ArcGIS Enterprise. For more detail on the contents shipped with the ArcGIS StreetMap Premium Custom Roads product, see [Contents](#) in the Reference section at the end of this document.

The Custom Roads edition of StreetMap Premium enables a specific capability for routing—seamlessly routing on both custom roads and commercial streets. Once integrated, this data can be used across the ArcGIS platform within ArcGIS Pro, ArcGIS Enterprise, and even packaged for use in ArcGIS Navigator, provided it is licensed accordingly.

The StreetMap Premium Custom Roads file geodatabase is in the projected coordinate system of WGS84 Web Mercator (Auxiliary Sphere). Within the StreetMap Premium Custom Roads file geodatabase, there are three empty feature classes that a geographic information system (GIS) analyst can either digitize or load roads into. Once the custom roads are added and the network dataset is rebuilt, the combined network is ready for routing.

StreetMap Premium Custom Roads is designed to be edited within ArcGIS Pro. When digitizing new features, street network connectivity and attribute requirements are automatically enforced using editing templates that are part of the ArcGIS Pro document.

**Note: The StreetMap Premium Custom Roads dataset is provided as a download from My Esri or on flash drive media in Read-Only format. After you copy and unzip the data to a local drive, make sure that the dataset (.gdb and .aprxF) is set to a non-restricted or non-read-only setting before beginning any editing.**

StreetMap Premium Custom Roads supports editing of three Custom Roads feature classes. It is not designed for editing any other feature classes; for example, edits should not be made to the Routing\_Streets layer (with the exception of adding vertices to connect custom streets, note that the provided editing templates automatically add vertices where needed to maintain street connectivity). This document describes the structure of the three Custom Roads feature classes and requirements for creating content within them.

## **Technical restrictions**

The following technical restrictions apply to StreetMap Premium Custom Roads:

- The customer is responsible for the creation and maintenance of any new networks.
- The customer is responsible for the transfer of their custom networks to new releases of StreetMap Premium.

- The customer can use the Custom Roads data only on the machines or mobile devices that StreetMap Premium Custom Roads is licensed for.
- Should the customer not renew their subscription to StreetMap Premium Custom Roads, the customer must remove and stop using the dataset.
- Custom Roads is only supported for use in ArcGIS Pro, ArcGIS Enterprise, and ArcGIS Navigator.

## **Licensing requirements**

The following licensing requirements are needed to use StreetMap Premium Custom Roads in ArcGIS software:

- **ArcGIS Pro:** To use within ArcGIS Pro, a StreetMap Premium license for ArcGIS Desktop is required. This license includes the StreetMap Premium extension for your region, for example, Asia Pacific, Europe, Latin America, Middle East and Africa, or North America, that allows access to the network dataset and the Locators. In ArcGIS Pro, check for the StreetMap Premium extension under Settings > Licensing > Esri Extensions, or if you already have an ArcGIS Pro project open, browse to Project > Licensing > Esri Extensions to view the list of extensions.

**Note:** With ArcGIS Pro 3.3 and 3.3.1, there is a known issue with the [Create Mobile Map Package](#) tool that affects the rebuilding of the network. As a workaround, use ArcGIS Pro 3.2.4 or earlier or Pro 3.3.2 or later to avoid this issue.

- **ArcGIS Enterprise:** To use within ArcGIS Enterprise, a StreetMap Premium license for ArcGIS Server is required. This license includes the StreetMap Premium extension for ArcGIS Pro and ArcGIS Enterprise for your region, for example, Asia Pacific, Europe, Latin America, Middle East and Africa, or North America, that allow publishing routing services with the custom network dataset and geocoding services with the Locators. In ArcGIS Server Manager, check for the StreetMap Premium extension under Site > Software Authorizations. In ArcGIS Pro, see above. The StreetMap Premium Custom Roads file geodatabase is not an enterprise geodatabase and may not be loaded into an enterprise geodatabase for editing purposes. Your street data may be edited in an enterprise geodatabase first and then transferred to the empty Custom\_Streets feature class in the StreetMap Premium Custom Roads file geodatabase for connection to the network dataset.

ArcGIS Enterprise users may benefit from increased routing service performance over large geographic areas by converting the StreetMap Premium Custom Roads network dataset in file geodatabase (.gdb) format to an SQLite mobile geodatabase format prior to publishing a routing service. The .gdb format is converted to the uncompressed mobile geodatabase format when creating a mobile map package in ArcGIS Pro. See [Convert file geodatabase to uncompressed mobile file geodatabase](#).

- **ArcGIS Navigator:** To create a custom map for use in Navigator, the author must be within ArcGIS Pro and have a StreetMap Premium Custom Roads license for ArcGIS Desktop or ArcGIS Server. This license includes the StreetMap Premium extension for your region, for example, Asia Pacific, Europe, Latin America, Middle East and Africa, or North America. To consume and use custom Navigator maps that ArcGIS Pro has packaged, each Navigator field worker must have an ArcGIS Navigator license.

Creating mobile map packages with the [Create Mobile Map Package](#) tool in ArcGIS Pro 3.2.2 or later will result in .mmpk files where geocoding is only supported in the following versions:


1. ArcGIS Navigator iOS (22.1.0) or ArcGIS Navigator Android (22.1.0).
2. ArcGIS Runtime 100.14.1 or later.

Use ArcGIS Pro 3.2 or later to create mobile map packages that take advantage of an updated compression routine for StreetMap Premium locator files. Using ArcGIS Pro 2.9.x or earlier to create mobile map packages will result in slightly larger .mmpk files overall.

# Layer descriptions

Custom data is put into three feature classes; each feature class is described in more detail below. The feature classes reside within the Routing feature dataset and participate in the Routing\_ND network dataset.

## *Custom Data Layers used for editing*



## ***Custom\_Streets***

[Custom\\_Streets](#) is a line feature class storing street segment geometry and attribution. For routing behavior to work correctly, at least one of the following rules must be followed:

- The endpoint of a Custom\_Streets segment must snap to the endpoint of a Routing\_Streets segment or snap to the endpoint of another Custom\_Streets segment.
- The endpoint of a Custom\_Streets segment must snap to a vertex of a Routing\_Streets segment or snap to the vertex of another Custom\_Streets segment.  
Additionally, a Custom\_Streets\_Override point must be placed on top of this intersection.
- A vertex of a Custom\_Streets segment must snap to a vertex of a Custom\_Streets or Routing\_Streets vertex. Additionally, a Custom\_Streets\_Override point must be placed on top of this intersection.
- The editing templates described in the [next section](#) help you adhere to the above rules. The editing templates automatically add an endpoint or split a Custom\_Streets segment if connecting to a midpoint without a vertex or add a vertex to the Routing\_Streets segment (if one doesn't already exist) and a Custom\_Streets\_Override point for street connectivity. If not using the editing templates, you will have to add these manually after appending or digitizing your custom streets.

## ***Custom\_Streets\_Override***

[Custom\\_Streets\\_Override](#) a point feature class storing street junction geometry and attribution. For routing behavior to work correctly, the following rules must be followed:

- A Custom\_Streets\_Override point is required at the intersection of a Custom\_Streets endpoint and a Routing\_Streets vertex, as well as at the intersection of a Custom\_Streets endpoint and a Custom\_Streets vertex.
- A Custom\_Streets\_Override point is required at the intersection of a Custom\_Streets vertex and a Routing\_Streets vertex, as well as at the intersection of a Custom\_Streets vertex and another Custom\_Streets vertex.
- A Custom\_Streets\_Override point should be placed at the intersection of a Custom\_Streets endpoint and a Routing\_Streets endpoint, as well as at the intersection of a Custom\_Streets

endpoint and another Custom\_Streets endpoint. In this case the Override point is used for tracking purposes, and not for network connectivity.

## ***Custom\_Turns***

[Custom\\_Turns](#) is a line feature class storing street turn geometry and attribution. A Custom\_Turns segment is only needed to model turn restrictions, and it is not required. For routing turn behavior to work correctly, the following rules must be followed:

- A Custom\_Turns segment must snap to each street edge that is part of the turn.
- The directionality of the line segment must be considered, going from the first street edge to the second street edge modeling the turn. Multi-edge turns are also supported, so there can be more than two street edges considered.
- The ObjectId attributes of the first street edge must be populated within the Edge1FID field, and the ObjectId of the second street edge must be populated within the Edge2FID field.


**Note:** If the ObjectId of a street edge changes, the associated value in the turn feature also needs to be updated.

- To restrict a turn, you must populate the RST\_... fields in the Custom\_Turns feature class with a "Yes" value for each type of vehicle that is restricted from making that turn or a "No" value for each type of vehicle for which the turn does not apply.

## **Editing templates**

The StreetMap Premium Custom Roads project (used within ArcGIS Pro) includes editing templates to help manage the properties of [Custom\\_Streets](#) when they are digitized or edited. Editing templates are a standard feature of ArcGIS Pro and can greatly help manage the effort of creating new features. Your organization may also choose to create new templates specific to your editing needs. The following templates are part of the ArcGIS Pro project.

### *Editing Templates within the Custom Roads ArcGIS Pro Project*



## Custom Streets

- **Connect Custom Street to Custom Street:** Used to connect a Custom Street to a Custom Street. When connecting a new Custom Street endpoint to a pre-existing Custom Street, the pre-existing segment will be split.
- **Connect Custom Street to Routing Street:** Used to connect a Custom Street to a Routing Street. When connecting a Custom Street endpoint to a Routing Street, the Routing Street will have a vertex created. A Custom Streets Override point will automatically be created at this intersection.

The following applies to both editing templates above:

- The FT\_KPH and TF\_KPH fields define the speed limit and have default values of 40 kilometers per hour (kph) or 25 miles per hour (mph).
- The STREET\_NAME field should be populated.
- The PAVED field (Yes or No values) is used within travel modes. When set to No, the streets are avoided when using the following travel modes: Driving Time, Driving Distance, Trucking Time, and Trucking Distance. These streets are traversable when using the following travel modes: Rural Driving Time, Rural Driving Distance, Walking Time, and Walking Distance.

If you leave attributes of your custom streets as NULL, for example, the FT\_/\_TF\_MINUTES attributes, then the Minutes cost attribute automatically looks for the distance from the METERS field and the speed from the FT/TF\_KPH field and performs the calculation for you. Leaving the METERS field as 0 results in the distance calculation reverting to the (less accurate) planar distance in the Shape\_Length field.

**Note:** Advanced Network Analyst behavior such as one-way streets and travel restrictions may be enforced within your newly created Custom\_Streets features. This utilizes standard Network Analyst functionality, using the data model of StreetMap Premium Custom Roads. For example:

- A one-way street may be modeled by populating the FT\_RST\_... and TF\_RST\_... fields in the Custom\_Streets feature class for each type of vehicle with a "Yes" value if the vehicle is not allowed to travel in the given direction, and a "No" value if the vehicle is allowed to travel in that given direction. There are two fields, one for each direction of travel, and the fields are relative to the digitized direction of the street.
- A travel restriction may be modeled by populating the restriction attributes accordingly within the field values.

## Custom Streets Override


- **Custom Streets Override:** Used to identify where Custom\_Streets connect with Routing\_Streets. These must be captured for the purposes of updating the content when a new StreetMap Premium database is available.

## Managing Editing Templates

If you want to modify the default attributes in the existing StreetMap Premium (SMP) Custom Roads editing templates in ArcGIS Pro, perform the following steps:

1. On the **Edit** tab in the **Features** group, click **Manage Templates**. The **Manage Templates** pane appears.

2. In the **Manage Templates** pane, click the **Custom\_Streets** feature class. You will see the two SMP Custom Roads templates for 'Connect Custom Street to Custom Street' and 'Connect Custom Street to Routing Street'.
3. On the toolbar, click **Properties**  just above the 'Connect Custom Street to Custom Street' template. The **Template Properties** dialog box should display.
4. In the **Template Properties** dialog box, click 'Attributes' on the left.
5. Add your default value in the second column where it says **<Null>** next to the selected attribute and click the box to the right to make it show up in the editing template as visible.



6. Close the dialogs, and make sure to save the changes to the editing templates by saving your ArcGIS Pro project (.aprxF). Then continue with editing.

See [Configure a feature template](#) in the ArcGIS Pro help for other modifications or more information.


## Loading Pre-existing Street Segments

Although existing road features may be appended into the custom streets layers, the connectivity and attribute requirements for routing are not automatically enforced when appending. Additional editing to enforce network connectivity and to populate attribution is required if existing roads are appended to the custom streets layers. Refer to the [Layer descriptions](#) section above for the rules that will enforce network connectivity in your custom network.

## Tasks

The StreetMap Premium Custom Roads project (used within ArcGIS Pro) includes editing tasks to help you merge your own street data into the StreetMap Premium Custom\_Streets feature class and network dataset. Tasks are a standard feature of ArcGIS Pro and can greatly help manage merging data features. **You must have at least the ArcGIS Desktop Standard license to run the tools associated with the editing tasks.** The tasks use standard ArcGIS Pro tools as well as custom tools. The custom tools are contained in the SMP\_<Region>\_Custom\_Roads toolbox (.tbx). Your organization may also create new tasks specific to your editing needs. The following tasks and custom tools are part of the ArcGIS Pro project and summarized below.

## Tasks and custom tools within the Custom Roads ArcGIS Pro Project




## **Merge existing street data into StreetMap Premium network dataset**

In the ArcGIS Pro Tasks Pane, click each numbered task to review it. Double-click each Task to begin using the task. Use the 'Skip' or 'Next Step' button in ArcGIS Pro to review each of the following tasks and steps in more detail without performing any data editing or processing. This will give you an overall understanding of best practices for merging your existing street data into the StreetMap Premium network dataset. **For each consecutive release of the StreetMap Premium Custom Roads product, you should always maintain your data within one of the three feature classes: Custom\_Streets, Custom\_Streets\_Override and Custom\_Turns.** **Copy these feature classes into the next update of StreetMap Premium Custom Roads. Editing of Routing\_Streets or other feature classes and tables associated with the StreetMap Premium Custom Roads network dataset is against the terms and use of the product license, except as noted above in the Layer descriptions and Loading Pre-existing Streets Segments, where adding vertices may be required. If editing of Routing\_Streets or other feature classes and tables associated with the StreetMap Premium Custom Roads network is wanted for a different use or workflow than described herein, you are then responsible for maintaining the connectivity and correctness of all road segments and attributes and standard technical support will not be available for addressing potential issues encountered.**

With ArcGIS Pro, as you begin your editing, you will notice a default symbology for dirty areas of the network dataset (Routing\_ND) begin to appear in the map (see below).

Dirty areas allow you to see where edits to source features have been made since the last time the network dataset was built. Rectangles surround and highlight the portions of the network dataset that are out of date due to the edits. When you rebuild the network, only the dirty areas are rebuilt, which can be much faster than rebuilding the entire network. If properties of the network dataset are altered, the entire network dataset may be covered by a dirty area, indicating all the elements of the [network need to be rebuilt](#). When the network is successfully rebuilt, the rectangles should disappear from the map.

### Dirty areas in the Custom Roads ArcGIS Pro project



## Task 1: Assess your street data

In Task 1, steps are given to examine and prepare your own street data prior to merging with StreetMap Premium data. This task walks you through some attribute and geometry checks to ensure that your data is ready for merging.

## Task 2: Prepare your street data for merging

This task helps you to identify and correct intersection connectivity. For your network dataset to function properly, your street data must be well connected at intersections. This task guides you through some steps to ensure good connectivity at intersections within your own street data.

The StreetMap Premium network dataset uses End Point connectivity. Consequently, for the road features in your network dataset to connect properly at intersections, your features must touch at end points. Note that if your data contains bridges, tunnels, overpasses, or other locations where streets cross over or under each other but do not physically connect, you will have to fix these locations if these features should not intersect.

## Task 3: Remove duplicate road segments

Task 3 helps you identify road segments in your street data that duplicate StreetMap Premium road segments, then review the selection and delete them. The **Select Duplicate Street Features** tool is provided to help accomplish this task.

## Task 4: Identify and fix remaining geometry issues

This task uses the **Create Topology to Check Connectivity** tool to create a topology with rules to look for common causes of connectivity problems.

The tool creates a new feature dataset with a copy of your streets in the specified workspace. Then it creates a topology and adds rules to it which help identify areas of problem geometry.

## Task 5: Append your streets to Custom\_Streets

This task helps you transfer your roads into the empty Custom\_Streets feature class for use with the StreetMap Premium dataset. It also helps you transfer any relevant attributes from your original data.

## Task 6: Connect Custom\_Streets to Routing\_Streets

To ensure good network connectivity, the features in Custom\_Streets must intersect with the street features in Routing\_Streets. If you are merging existing data into StreetMap Premium, it is likely your own roads will not be coincident with the existing StreetMap Premium data. Intersection points will fall short of connecting or will have dangles. Additionally, points of connection must have either feature end points or vertices with coincident override junctions. Use this task to correct these problems and ensure good network dataset connectivity between Custom\_Streets and Routing\_Streets. The **Custom Streets Elevation Fix, Ensure Intersection Connectivity**, and **Snap to SMP** tools are provided to help accomplish this task.

## Task 7: Set up turns

Use this task to set up turns to control turn restrictions at intersections. There are many types of turn features and restrictions that can be added to network datasets. The [ArcGIS Network Analyst data prep tutorial](#) provides detailed instructions and graphics to guide you in digitizing turns. These tutorials may be reviewed before getting started adding or editing turn restrictions.

## Task 8: Build your network dataset

Use the **Build Network** tool to incorporate your network dataset edits into the StreetMap Premium network dataset (Routing\_ND). If you get build errors, review them along with the [Common build errors](#) documentation page. Fix any errors and run the Build Network tool again.

## Task 9: Verify network connectivity

This task will help you assess whether your network dataset is adequately connected using network functions like Service Area and Route analyses.

## Task 10: Create and share a mobile map package

In this task, use the **Create Mobile Map Package** tool to package your custom network dataset along with mapping layers, the vector tile package, and a locator for mobile use. Your own custom streets and other mapping layers should be added on top of the vector tile package to be visible in the final mobile map package. Since the StreetMap Premium Custom Roads extent is for the entire region, do not use the Default extent setting; instead use your Area of Interest to create a small package size efficient for mobile use. When packaging the network dataset, warnings about live traffic may be ignored because a live traffic service cannot be used in a mobile map package. Similarly, other online mapping services cannot be packaged for mobile use. Note that the Navigator app requires a map package to contain a locator to be recognized as a valid map package.

Then, use the **Share Package** tool to share your package with your ArcGIS organization so users can download the package for use with the Navigator app.

### ***Convert file geodatabase to uncompressed mobile file geodatabase***

ArcGIS Enterprise users may benefit from increased routing service performance over large geographic areas by converting the StreetMap Premium Custom Roads network dataset in file geodatabase format (.gdb) to an SQLite mobile geodatabase format prior to publishing a routing service. The .gdb format is converted to the uncompressed mobile geodatabase format when creating a mobile map package in ArcGIS Pro.

To extract the network dataset from the mobile map package, import your mobile map package into ArcGIS Pro by clicking the Insert tab, and clicking Import Map. Then, browse to your mobile map package location to select it. After the mobile map package has been imported, it is located here (by default), for example:

C:\Users\<UserName>\Documents\ArcGIS\Packages\Morocco\_<unique#>\commondata folder.

The network dataset in mobile geodatabase format consists of the <Region>.tn folder and the <Region>.geodatabase file. When publishing a routing service using the Publish Routing Services utility, specify the pathname to the <Region>.geodatabase for the network dataset input parameter (-n). See the [Publish Routing Services utility](#) for command syntax and additional parameters.

## Update process

Once data is captured into the custom data layers, your organization will want to use these features with future StreetMap Premium updates. The following process should be followed for migrating custom streets features into a new update of StreetMap Premium:

1. [Append](#) the Custom\_Streets, Custom\_Streets\_Override, and Custom\_Turns features from your existing version of StreetMap Premium into the equivalent feature classes in the new version of StreetMap Premium.
2. Review the segments and points that you just loaded into the new StreetMap Premium database. Compare the Custom\_Streets segments against the Routing\_Streets segments to identify situations where updates to the Routing\_Streets layer will impact connectivity to your Custom\_Streets.
  - Identify any situation where a Routing\_Streets segment now represents a Custom\_Streets segment.
    - In these situations, delete your Custom\_Streets segment to avoid duplication of streets.
    - Edit any Custom\_Streets segments that may have been connected to your newly deleted feature, as appropriate.
  - Identify any situation where a Routing\_Streets segment has moved resulting in your Custom\_Streets segments no longer being connected to it.
    - Edit and move the endpoint of your Custom\_Streets to be coincident to the Routing\_Streets. If a Custom\_Street\_Override is present at this location, also edit and move it.

**Note:** To identify these situations and locations, you may want to use a [topology rule](#).

3. Review the Custom\_Turns segments that you just loaded into the new StreetMap Premium database. Identify any situations where updates to the Routing\_Streets layer will impact the connectivity and snapping of your Custom\_Turns segments.
  - For example, if a Routing\_Streets segment has moved, move the Custom\_Turns segment to snap to the segment once again.

**Note:** To identify these situations and locations, you may want to use a [topology rule](#).

4. Run [Update by Geometry](#) on the updated Custom\_Turns feature class.
5. Select all Routing\_Streets segments that intersect the Custom\_Streets segments. Run [Integrate](#) with a cluster tolerance of 0. This will insert a vertex where these two locations intersect. Note that a Custom\_Streets\_Override point must exist at this intersection, or network connectivity will not be enforced.
6. Run [Build Network](#). This will connect the network dataset for routing using the newly loaded Custom\_Streets features.
7. Test the network to ensure connectivity by using test stop locations and the ArcGIS Network Analyst extension.

**Note:** Where the addition of a Custom\_Streets feature may have split a Routing\_Streets feature in the original data, this update process does not split the Routing\_Streets, and connectivity is enforced via vertex and Custom\_Street\_Override in the new data.

## Reference documents

Learn more about ArcGIS StreetMap Premium:

- [ArcGIS StreetMap Premium Resources](#)
- [ArcGIS StreetMap Premium on ArcGIS StreetMap Premium website](#)
- [ArcGIS StreetMap Premium in ArcGIS Pro help](#)

Learn more about network datasets and how to build one:

- [What is a network dataset?](#)
- [Routing with StreetMap Premium in ArcGIS Pro](#)

Learn more about the Network Analyst extension:

- [ArcGIS Network Analyst extension](#)
- [An overview of the Network Analyst toolbox](#)

Learn more about creating turns:

- [Turns](#)
- [Create Turn Feature Class](#)

Learn more about setting directions:

- [Configure directions](#)

Learn more about preparing maps for use with ArcGIS Navigator:

- [Prepare maps](#)

## Support

For technical restrictions, system requirements, and other support information regarding ArcGIS StreetMap Premium Custom Roads, see [ArcGIS StreetMap Premium](#) on the ArcGIS StreetMap Premium website.

# Data dictionary

## *Point layers*

### **Custom Streets Override Points (Custom\_Streets\_Override)**

The Custom Streets Override Points (Custom\_Streets\_Override File Geodatabase Feature Class) point layer is an empty feature class to contain connection points indicating where connectivity occurs mid-span along merged line features of the dissolved network dataset, Routing\_ND.

This layer contains the following fields:

Field Name	Description	Values
OBJECTID	Internal feature number	Sequential unique whole numbers that are automatically generated.
Shape	Feature geometry	Coordinates defining the features.
ELEV	Relative Z-level	The relative vertical position of connection points that indicate where connectivity occurs mid-span along the merged line features of the dissolved network dataset, Routing_ND. The ELEV field is set by either the geodatabase or template default; values are generally <Null>. Values must be <Null> for segments with mid-span vertex connectivity.

## *Line layers*

### **Custom Streets for network (Custom\_Streets)**

The Custom Streets for network (Custom\_Streets File Geodatabase Feature Class) line layer is an empty feature class to contain user-defined streets to be added to the existing network, Routing\_ND, for routing. Custom\_Streets has the same attribute schema as Routing\_Streets, except the values are blank or empty and are meant to be defined by the user. Additional attributes included after the Shape\_Length field are specific to Custom\_Streets and are intended for road speeds or custom street symbolization for use in creating mobile map packages.

This layer contains the following fields:

Field Name	Description	Values
OBJECTID	Internal feature number	Sequential unique whole numbers that are automatically generated.
Shape	Feature geometry	Coordinates defining the features.
FULL_STREET_NAME	Full Street Name	Full Street Name—this is the preferred street name. <b>Note:</b> It can also be a Route Number, Exit

Field Name	Description	Values
		Number, or Junction Name, if such a name is the preferred Street Name.
STREET_PREFIX_DIR	Street Name Prefix	Directional identifier that precedes the name of the road: see <a href="#">Directional Identifiers</a> for values.
STREET_PREFIX_TYPE	Street Type Before	Street Type of the Street Name that appears before the Base Name. Street Types such as "Calle" or "Rue".
STREET_NAME	Street Name Base	Base Name of the Street Name.
STREET_TYPE	Street Type After	Street Type of the Street Name that appears after the Base Name. Street Types such as "Ave", "Avenue", "Fry", "Hwy", "Rd", "St", "Trl", or "Walk".
STREET_DIR	Street Name Suffix	Directional identifier that follows the name of the road: see <a href="#">Directional Identifiers</a> for values.
STREET_NAME_DIRECTION	Street Highway Direction	Official directional identifier assigned to the highway that is the official direction and not necessarily the travel direction: see <a href="#">Direction on Sign</a> for values.
STREET_LANGUAGE	Street Name Language Code	The language associated with the street name.
STREET_NAME_CLASS	Street Name Class	Class of the Street Name: <Null> (StreetName is empty), 0 (StreetName is not a route number), or 1 (StreetName is a route number).
HIERARCHY	Hierarchy	Hierarchy is the order or rank assigned to network elements. A street network may have an attribute on the source features that breaks the roads down into classes: see <a href="#">Hierarchy</a> for values.
ROAD_CLASS	Road Class	Road Class is a combination of a variety of conditions: Ramp, Ferry Type, Controlled Access, Intersection Category, and Functional Class. See <a href="#">Road Classes</a> for values.
SPEED_CLASS	Speed Class	Classification for road speeds in the routing index: see <a href="#">Speed Classes</a> for values.

Field Name	Description	Values
MANEUVER_CLASS	Maneuver Class	Indicates type of maneuver at a Link: see <a href="#">Maneuver Class Codes</a> for values.
DRIVING_SIDE	Driving Side	Indicates the legal driving side of the country for the link: L (Left) or R (Right).
FT_TRAVEL_DIRECTION	From-To Travel Direction	Indicates if the traffic flow is allowed in the From direction for a Road Element or Ferry Connection: Y (Traffic is allowed in this direction), N (Traffic is not allowed in this direction), or <Null> (Not applicable). Used in live traffic feeds to match the OpenLR™ encoded locations to street segments. See <a href="#">Work with live traffic</a> in ArcGIS Pro help to learn more about OpenLR.
TF_TRAVEL_DIRECTION	To-From Travel Direction	Indicates if the traffic flow is allowed in the To direction for a Road Element or Ferry Connection: Y (Traffic is allowed in this direction), N (Traffic is not allowed in this direction), or <Null> (Not applicable). Used in live traffic feeds to match the OpenLR encoded locations to street segments. See <a href="#">Work with live traffic</a> in ArcGIS Pro help to learn more about OpenLR.
OPENLR_FRC	Functional Road Class for OpenLR	A classification based on the importance of the role that a Road Element or Ferry Connection performs in the connectivity of the total road network: 0 (Motorway), 1 (Major Road of High Importance), 2 (Other Major Road), 3 (Secondary Road), 4 (Local Connecting Road), 5 (Local Road Of High Importance), 6 (Local Road), 7 (Local Road Of Minor Importance), or 8 (Other Road). Used in live traffic feeds to match the OpenLR encoded locations to street segments. See <a href="#">Work with live traffic</a> in ArcGIS Pro help to learn more about OpenLR.
OPENLR_FOW	Form-of-Way for OpenLR	Relates to certain aspects of the physical form that a Road Element or Ferry Connection takes based on a number of physical and traffic

Field Name	Description	Values
		properties: 1 (Motorway), 2 (Multiple Carriageway), 3 (Single Carriageway), 4 (Roundabout), 5 (Traffic Square), 6 (Slip Road), or 7 (Other). Used in live traffic feeds to match the OpenLR encoded locations to street segments. See <a href="#">Work with live traffic</a> in ArcGIS Pro help to learn more about OpenLR.
SUPPLEMENTAL_GEO_BITSET	Supplemental Geometry Bit set	Provides a classification for road geometry types included for special or limited use.
TimeZoneID	Time Zone Identifier	Time Zone Identifier.
COUNTRY_REGION_CODE	Country or Region Code	Code for the Country or Region (country subdivision (state)): <a href="#">ISO 3166-2 codes</a> for the United States, and <a href="#">ISO 3166-1 codes</a> for all other countries.
ADMIN0_NAME	Country Name (In English)	Name of the Country.
ADMIN1_NAME	Level 1 Administrative Area Name	The name of the Level 1 Administrative Area (region, state, or province).
ADMIN1_ABBR	Level 1 Administrative Area Abbreviated Name	Two or three letter abbreviation for the Level 1 name.
F_ZLEV	Begin Level	Segments at ground level have level = 0, above ground level have level >0, and below ground level have level <0: Values range from +9 (highest) to -9 (lowest); 0 is ground Z Level.
T_ZLEV	End Level	Segments at ground level have level = 0, above ground level have level >0, and below ground level have level <0: Values range from +9 (highest) to -9 (lowest); 0 is ground Z Level.
METERS *	Length of the link	Lengths (meters) for the features. When features are created, the METERS field contains a <Null> value. When this value is <Null>, then the network dataset will utilize geodesic distances derived from the feature's geometry for distance calculation; if the user populates a

Field Name	Description	Values
		value in this field for a feature, then that value is used for distance calculation (the feature's geometry is not used for distance calculation).
FT_MINUTES	From-To All Week Traveling Time in Minutes	Average traveling time in network for the entire week in From-To direction in minutes: durations for the features calculated using segment length in meters and streets speed values from historical traffic data (if not <Null>). Historical traffic reflects driving patterns that provide average speeds over the years.
TF_MINUTES	To-From All Week Traveling Time in Minutes	Average traveling time in network for the entire week in To-From direction in minutes: durations for the features calculated using segment length in meters and streets speed values from historical traffic data (if not <Null>). Historical traffic reflects driving patterns that provide average speeds over the years.
FT_TRUCK_MINUTES	From-To Truck Traveling Time in Minutes	Defines truck traveling time calculation in the From-To direction (in minutes).
TF_TRUCK_MINUTES	To-From Truck Traveling Time in Minutes	Defines truck traveling time calculation in the To-From direction (in minutes).
FULL_STREET_NAME_ALT1	First Alternate Full Street Name	Alternate Full Street Name or Route Number including the Street Name Prefix, Street Name Suffix, Street Types, and Direction on Sign (for Route Numbers when available).
STREET_PREFIX_DIR_ALT1	First Alternate Name Prefix Directional Component	Street name prefix directionals for the features: see <a href="#">Directional Identifiers</a> for values.
STREET_PREFIX_TYPE_ALT1	First Alternate Name Prefix Type Component	Street name prefix types for the features such as "Boul", "Calle", "Rte", or "Rue".
STREET_NAME_ALT1	First Alternate Base part of the Full Street Name or Route Number	Base part of the Full Street Name, Route Number, or Ferry Route Name.

Field Name	Description	Values
STREET_TYPE_ALT1	First Alternate Name Type Component	Street name types for the features such as "Ave", "Blvd", "Fry", "Fwy", "Hwy", "Plz", "St", or "Trl".
STREET_DIR_ALT1	First Alternate Street Name Suffix	Directional identifier that follows the name of the road: see <a href="#">Directional Identifiers</a> for values.
STREET_NAME_DIRECTION_ALT1	First Alternate Route Directional	Directional information as determined by a governing authority: see <a href="#">Direction on Sign</a> for values.
STREET_LANGUAGE_ALT1	First Alternate Street Name Language Code	The language associated with the street name.
STREET_NAME_CLASS_ALT1	First Alternate Street Name Class	Class of the Street Name: <Null> (StreetNameAlt1 is empty), 0 (StreetNameAlt1 is not a route number), or 1 (StreetNameAlt1 is a route number).
FULL_STREET_NAME_ALT2	Second Alternate Full Street Name or Route Number	Alternate Full Street Name or Route Number including the Street Name Prefix, Street Name Suffix, Street Types, and Direction on Sign (for Route Numbers when available).
STREET_PREFIX_DIR_ALT2	Second Alternate Name Prefix Directional Component	Directional identifier that precedes the name of the road: see <a href="#">Directional Identifiers</a> for values.
STREET_PREFIX_TYPE_ALT2	Second Alternate Name Prefix Type Component	Street Type of the Street Name that appears before the Base Name. Street Types such as "Calle" or "Rue".
STREET_NAME_ALT2	Second Alternate Base part of the Full Street Name or Route Number	Base part of the Full Street Name, Route Number, or Ferry Route Name.
STREET_TYPE_ALT2	Second Alternate Name Type Component	Street name types for the features such as "Ave", "Blvd", "Fry", "Fwy", "Hwy", "Plz", "St", or "Trl".
STREET_DIR_ALT2	Second Alternate Name Suffix Directional Component	Street name suffix directionals for the features: see <a href="#">Directional Identifiers</a> for values.
STREET_NAME_DIRECTION_ALT2	Second Alternate Route Directional	Directional information as determined by a governing authority: see <a href="#">Direction on Sign</a> for values.

Field Name	Description	Values
STREET_LANGUAGE_ALT2	Second Alternate Street Name Language Code	The language associated with the street name.
STREET_NAME_CLASS_ALT2	Second Alternate Street Name Class	Class of the Street Name: <Null> (StreetNameAlt2 is empty), 0 (StreetNameAlt2 is not a route number), or 1 (StreetNameAlt2 is a route number).
FULL_STREET_NAME_ALT3	Third Alternate Full Street Name or Route Number	Alternate Full Street Name or Route Number including the Street Name Prefix, Street Name Suffix, Street Types, and Direction on Sign (for Route Numbers when available).
STREET_PREFIX_DIR_ALT3	Third Alternate Name Prefix Directional Component	Street name prefix directionals for the features: see <a href="#">Directional Identifiers</a> for values.
STREET_PREFIX_TYPE_ALT3	Third Alternate Name Prefix Type Component	Street name prefix types for the features such as "Boul", "Calle", "Rte", or "Rue".
STREET_NAME_ALT3	Third Alternate Base part of the Full Street Name or Route Number	Base part of the Full Street Name, Route Number, or Ferry Route Name.
STREET_TYPE_ALT3	Third Alternate Name Type Component	Street name types for the features such as "Ave", "Blvd", "Fry", "Fwy", "Hwy", "Plz", "St", or "Trl".
STREET_DIR_ALT3	Third Alternate Name Suffix Directional Component	Street name suffix directionals for the features: see <a href="#">Directional Identifiers</a> for values.
STREET_NAME_DIRECTION_ALT3	Third Alternate Route Directional	Directional information as determined by a governing authority: see <a href="#">Direction on Sign</a> for values.
STREET_LANGUAGE_ALT3	Third Alternate Street Name Language Code	The language associated with the street name.
STREET_NAME_CLASS_ALT3	Third Alternate Street Name Class	Class of the Street Name: <Null> (StreetNameAlt3 is empty), 0 (StreetNameAlt3 is not a route number), or 1 (StreetNameAlt3 is a route number).
FULL_STREET_NAME_ALT4	Fourth Alternate Full Street Name or Route Number	Alternate Full Street Name or Route Number including the Street Name Prefix, Street Name Suffix, Street

Field Name	Description	Values
		Types, and Direction on Sign (for Route Numbers when available).
STREET_PREFIX_DIR_ALT4	Fourth Alternate Name Prefix Directional Component	Street name prefix directionals for the features: see <a href="#">Directional Identifiers</a> for values.
STREET_PREFIX_TYPE_ALT4	Fourth Alternate Name Prefix Type Component	Street name prefix types for the features such as "Boul", "Calle", "Rte", or "Rue".
STREET_NAME_ALT4	Fourth Alternate Base part of the Full Street Name or Route Number	Base part of the Full Street Name, Route Number, or Ferry Route Name.
STREET_TYPE_ALT4	Fourth Alternate Name Type Component	Street name types for the features such as "Ave", "Blvd", "Fry", "Fwy", "Hwy", "Plz", "St", or "Trl".
STREET_DIR_ALT4	Fourth Alternate Name Suffix Directional Component	Street name suffix directionals for the features: see <a href="#">Directional Identifiers</a> for values.
STREET_NAME_DIRECTION_ALT4	Fourth Alternate Route Directional	Directional information as determined by a governing authority: see <a href="#">Direction on Sign</a> for values.
STREET_LANGUAGE_ALT4	Fourth Alternate Street Name Language Code	The language associated with the street name.
STREET_NAME_CLASS_ALT4	Fourth Alternate Street Name Class	Class of the Street Name: <Null> (StreetNameAlt4 is empty), 0 (StreetNameAlt4 is not a route number), or 1 (StreetNameAlt4 is a route number).
FERRY	Ferry Type	Indicates if the link is a ferry: Y (Ferry) or N (Not a Ferry).
CONTROLLED_ACCESS	Controlled Access	Controlled Access indicates roads that are separately digitized, high-speed roads where all legal traffic movements are controlled, allowing uninterrupted high speed traffic flow: Y (Controlled Access) or N (Not Controlled Access). <b>NOTE:</b> These roads constitute the interstate and freeway network in the U.S. and the motorway network in Europe.
PAVED	Paved	Indicates the road is paved (made of materials that create a solid surface,

Field Name	Description	Values
		such as concrete, asphalt, brick or cobblestone): Y (Paved) or N (Not paved).
FT_RST_ROAD_UNDER_CONSTR	From-Toward Roads Under Construction Prohibited	Indicates if the link in the From-Toward direction is affected by construction and closed to public use: Y (Link is closed) or N (Link is not closed). <b>NOTE:</b> When a road is closed, no traffic can travel on the road for the duration of the construction.
TF_RST_ROAD_UNDER_CONSTR	Toward-From Roads Under Construction Prohibited	Indicates if the link in the Toward-From direction is affected by construction and closed to public use: Y (Link is closed) or N (Link is not closed). <b>NOTE:</b> When a road is closed, no traffic can travel on the road for the duration of the construction.
PUBLIC_ROAD	Public Access	Indicates if the link allows public access: Y (Public access allowed) or N (Public access not allowed).
CARPOOL_ROAD	Carpool Road	Identifies a link where, at specific times, all lanes serve as carpool lanes: Y (Carpool Road) or N (Not a Carpool Road).
EXPRESS_LANE	Express Lane	Identifies a link that serves as an express lane: Y (Express Lane) or N (Not an Express Lane).
RST_TOLL_ROAD_AUTOMOBILES	Avoid Toll Roads for Passenger Cars	Indicates if the Usage Fee Required (toll) applies to Passenger Cars: Y (Applies) or N (Does not apply). <b>NOTE:</b> The Usage Fee Required is applied to all links that are affected by any type of toll and can be used for routing and guidance (for example, for enabling avoidance of toll roads).
RST_TOLL_ROAD_TRUCKS	Avoid Toll Roads for Trucks	Indicates if the Usage Fee Required (toll) applies to Trucks or Deliveries: Y (Applies) or N (Does not apply). <b>NOTE:</b> The Usage Fee Required is applied to all links that are affected by any type of toll and can be used for routing and guidance (for example, for enabling avoidance of toll roads).

<b>Field Name</b>	<b>Description</b>	<b>Values</b>
FT_RST_AUTOMOBILES	From Automobiles Restricted	Indicates if Automobiles are legally restricted from using the link in the From direction: Y (Applies) or N (Does not apply).
TF_RST_AUTOMOBILES	Toward Automobiles Restricted	Indicates if Automobiles are legally restricted from using the link in the Toward direction: Y (Applies) or N (Does not apply).
FT_RST_BUSES	From Buses Restricted	Indicates if Buses are legally restricted from using the link in the From direction: Y (Applies) or N (Does not apply).
TF_RST_BUSES	Toward Buses Restricted	Indicates if Buses are legally restricted from using the link in the Toward direction: Y (Applies) or N (Does not apply).
FT_RST_TAXIS	From Taxis Restricted	Indicates if Taxis are legally restricted from using the link in the From direction: Y (Applies) or N (Does not apply).
TF_RST_TAXIS	Toward Taxis Restricted	Indicates if Taxis are legally restricted from using the link in the Toward direction: Y (Applies) or N (Does not apply).
RST_PEDESTRIANS	Pedestrians Restricted	Indicates if Pedestrians are legally restricted from using the link: Y (Applies) or N (Does not apply).
FT_RST_TRUCK_DELIVERY_ONLY	From Trucks Restricted (Except Local Deliveries)	Indicates if Trucks are allowed only to make a Delivery in the local vicinity using the link in the From direction: Y (Applies) or N (Does not apply).
TF_RST_TRUCK_DELIVERY_ONLY	Toward Trucks Restricted (Except Local Deliveries)	Indicates if Trucks are allowed only to make a Delivery in the local vicinity using the link in the Toward direction: Y (Applies) or N (Does not apply).
RST_THROUGH_TRAFFIC	Through Traffic Restricted	Indicates if Automobile Through Traffic is legally restricted from using the link: Y (Applies) or N (Does not apply).
FT_RST_TRUCKS	From Trucks Restricted	Indicates if Trucks are legally restricted from using the link in the From direction: Y (Applies) or N (Does not apply).

Field Name	Description	Values
TF_RST_TRUCKS	Toward Trucks Restricted	Indicates if Trucks are legally restricted from using the link in the Toward direction: Y (Applies) or N (Does not apply).
FT_RST_EMERGENCY_VEHICLES	From Emergency Vehicles Restricted	Indicates if Emergency Vehicles are legally restricted from using the link in the From direction: Y (Applies) or N (Does not apply).
TF_RST_EMERGENCY_VEHICLES	Toward Emergency Vehicles Restricted	Indicates if Emergency Vehicles are legally restricted from using the link in the Toward direction: Y (Applies) or N (Does not apply).
FT_RST_MOTORCYCLES	From Motorcycles Restricted	Indicates if Motorcycles are legally restricted from using the link in the From direction: Y (Applies) or N (Does not apply).
TF_RST_MOTORCYCLES	Toward Motorcycles Restricted	Indicates if Motorcycles are legally restricted from using the link in the Toward direction: Y (Applies) or N (Does not apply).
FT_RST_HEIGHT	From Vehicle Height Restriction	Indicates a Transport Access legal vehicle height restriction in the From direction on the link: Heights (meters) for the features.
TF_RST_HEIGHT	Toward Vehicle Height Restriction	Indicates a Transport Access legal vehicle height restriction in the Toward direction on the link: Heights (meters) for the features.
FT_RST_WEIGHT	From Vehicle Weight Restriction	Indicates a Transport Access legal vehicle (total) weight restriction in the From direction on the link: Weights (kilograms) for the features.
TF_RST_WEIGHT	Toward Vehicle Weight Restriction	Indicates a Transport Access legal vehicle (total) weight restriction in the Toward direction on the link: Weights (kilograms) for the features.
FT_RST_WEIGHT_PER_AXLE	From Vehicle Weight per Axle Restriction	Indicates a Transport Access legal vehicle weight per axle restriction in the From direction on the link: Weights (kilograms) for the features.
TF_RST_WEIGHT_PER_AXLE	Toward Vehicle Weight per Axle Restriction	Indicates a Transport Access legal vehicle weight per axle restriction in the Toward direction on the link:

Field Name	Description	Values
		Weights (kilograms) for the features.
FT_RST_LENGTH	From Vehicle Length Restriction	Indicates a Transport Access legal vehicle length restriction in the From direction on the link: Lengths (meters) for the features.
TF_RST_LENGTH	Toward Vehicle Length Restriction	Indicates a Transport Access legal vehicle length restriction in the Toward direction on the link: Lengths (meters) for the features.
FT_RST_WIDTH	From Vehicle Width Restriction	Indicates a Transport Access legal vehicle width restriction in the From direction on the link: Widths (meters) for the features.
TF_RST_WIDTH	Toward Vehicle Width Restriction	Indicates a Transport Access legal vehicle width restriction in the Toward direction on the link: Widths (meters) for the features.
FT_RST_KINGPIN_REAR_AXL_LENGTH	From Vehicle Length (from Kingpin to Rear Axle) Restriction	Indicates a Transport Access legal vehicle length (from Kingpin to Rear Axle) restriction in the From direction on the link: Lengths (meters) for the features.
TF_RST_KINGPIN_REAR_AXL_LENGTH	Toward Vehicle Length (from Kingpin to Rear Axle) Restriction	Indicates a Transport Access legal vehicle length (from Kingpin to Rear Axle) restriction in the Toward direction on the link: Lengths (meters) for the features.
FT_RST_TRUCK_TRAILERS	From Trailer Type Restriction	Indicates a Transport Access trailer type legal restriction in the From direction on the link: <Null> (Restriction does not apply), 1 (Truck with one or more trailers is restricted), 2 (Truck with two or more trailers is restricted), or 3 (Truck with three or more trailers is restricted).
TF_RST_TRUCK_TRAILERS	Toward Trailer Type Restriction	Indicates a Transport Access trailer type legal restriction in the Toward direction on the link: <Null> (Restriction does not apply), 1 (Truck with one or more trailers is restricted), 2 (Truck with two or more trailers is restricted), or 3 (Truck with three or more trailers is restricted).

Field Name	Description	Values
FT_RST_SEMI_TRACTOR_TRAILERS	From Trailer Type (Semi or Tractor with one or more trailers) Restriction	Indicates a Transport Access trailer type (Semi or Tractor with one or more trailers) legal restriction in the From direction on the link: Y (Restriction applies), N (Restriction does not apply), or No value (Information is unknown).
TF_RST_SEMI_TRACTOR_TRAILERS	Toward Trailer Type (Semi or Tractor with one or more trailers) Restriction	Indicates a Transport Access trailer type (Semi or Tractor with one or more trailers) legal restriction in the Toward direction on the link: Y (Restriction applies), N (Restriction does not apply), or No value (Information is unknown).
FT_RST_ANY_HAZMAT	From All Hazardous Material Types Restriction	Indicates a Transport Access hazardous material type—Explosives (Class 1), Gas, Flammable, Flammable solid or Combustible, Organic, Poison, Radioactive, Corrosive, Other, Any Hazardous Material, Poisonous Inhalation Hazard (PIH), Goods Harmful for Water, or Explosive and Flammable—legal restriction in the From direction on the link: Y (Restriction applies), N (Restriction does not apply), or No value (Information is unknown).
TF_RST_ANY_HAZMAT	Toward All Hazardous Material Types Restriction	Indicates a Transport Access hazardous material type—Explosives (Class 1), Gas, Flammable, Flammable solid or Combustible, Organic, Poison, Radioactive, Corrosive, Other, Any Hazardous Material, Poisonous Inhalation Hazard (PIH), Goods Harmful for Water, or Explosive and Flammable—legal restriction in the Toward direction on the link: Y (Restriction applies), N (Restriction does not apply), or No value (Information is unknown).
FT_RST_AXLE_COUNT	From Number of Axles Restriction	Indicates a Transport Access number of axles legal restriction in the From direction on the link: <Null> (Restriction does not apply), 1 (Two or more axles are restricted), 2 (Three or more axles are restricted), 3 (Four or more axles are

Field Name	Description	Values
		restricted), 4 (Five or more axles are restricted), or 5 (Six or more axles are restricted).
TF_RST_AXLE_COUNT	Toward Number of Axles Restriction	Indicates a Transport Access number of axles legal restriction in the Toward direction on the link: <Null> (Restriction does not apply), 1 (Two or more axles are restricted), 2 (Three or more axles are restricted), 3 (Four or more axles are restricted), 4 (Five or more axles are restricted), or 5 (Six or more axles are restricted).
FT_RST_SINGLE_AXLE_VEHICLE	From Number of Axles (Single Axle) Restriction	Indicates a Transport Access number of axles (single axle) legal restriction in the From direction on the link: Y (Restriction applies), N (Restriction does not apply), or No value (Information is unknown).
TF_RST_SINGLE_AXLE_VEHICLE	Toward Number of Axles (Single Axle) Restriction	Indicates a Transport Access number of axles (single axle) legal restriction in the Toward direction on the link: Y (Restriction applies), N (Restriction does not apply), or No value (Information is unknown).
FT_RST_TANDEM_AXLE_VEHICLE	From Number of Axles (Tandem Axle) Restriction	Indicates a Transport Access number of axles (tandem axle) legal restriction in the From direction on the link: Y (Restriction applies), N (Restriction does not apply), or No value (Information is unknown).
TF_RST_TANDEM_AXLE_VEHICLE	Toward Number of Axles (Tandem Axle) Restriction	Indicates a Transport Access number of axles (tandem axle) legal restriction in the Toward direction on the link: Y (Restriction applies), N (Restriction does not apply), or No value (Information is unknown).
FT_RST_PREF_TRUCK	From STAA, TD, and Local Preferred Route	Indicates a Transport preferred route is part of the Surface Transportation Assistance Act (STAA) in the U.S. or a federally-designated truck route in other countries, TD (Truck Designated route – state-designated highway network in the U.S. or a state-designated truck route in other countries), and Local (locally-designated truck route) in the From

Field Name	Description	Values
		direction on the link: Y (Preferred route applies), N (Preferred route does not apply), or No value (Information is unknown).
TF_RST_PREF_TRUCK	Toward STAA, TD, and Local Preferred Route	Indicates a Transport preferred route is part of the Surface Transportation Assistance Act (STAA) in the U.S. or a federally-designated truck route in other countries, TD (Truck Designated route – state-designated highway network in the U.S. or a state-designated truck route in other countries), and Local (locally-designated truck route) in the Toward direction on the link: Y (Preferred route applies), N (Preferred route does not apply), or No value (Information is unknown).
FT_RST_PREF_HAZMAT	From All Hazardous Materials and Goods Preferred Route	Indicates a Transport preferred route for transporting—National Repository of non-radioactive Hazardous Materials (NRHM), Class 1 (Explosive hazardous materials), Poisonous Inhalation Hazard (PIH) materials, Medical Waste, or Radioactive hazardous materials, or General Hazardous Goods—in the From direction on the link: Y (Preferred route applies), N (Preferred route does not apply), or No value (Information is unknown).
TF_RST_PREF_HAZMAT	Toward All Hazardous Materials and Goods Preferred Route	Indicates a Transport preferred route for transporting—National Repository of non-radioactive Hazardous Materials (NRHM), Class 1 (Explosive hazardous materials), Poisonous Inhalation Hazard (PIH) materials, Medical Waste, or Radioactive hazardous materials, or General Hazardous Goods—in the Toward direction on the link: Y (Preferred route applies), N (Preferred route does not apply), or No value (Information is unknown).
FT_RST_SPEED_LIMIT	From Speed Limit	Indicates the posted or legal speed limit applicable to automobiles in the From travel direction on a road: Speed limits (kilometers per hour

Field Name	Description	Values
		(kph)) for the features; <Null> (Unknown) or 999 (The road allows an unlimited speed).
TF_RST_SPEED_LIMIT	Toward Speed Limit	Indicates the posted or legal speed limit applicable to automobiles in the To travel direction on a road: Speed limits (kph) for the features; <Null> (Unknown) or 999 (The road allows an unlimited speed).
FT_RST_TRUCK_SPEED_LIMIT	From Truck Speed Limit	Indicates the speed limit applicable to trucks in the From direction on the link in kph.
TF_RST_TRUCK_SPEED_LIMIT	Toward Truck Speed Limit	Indicates the speed limit applicable to trucks in the Toward direction on the link in kph.
RST_PEDESTRIAN_PREFERRED	Preferred Pedestrian Route Restriction	Identifies a road segment suitable for pedestrian navigation: Y (Suitable for pedestrian navigation), N (Not suitable for pedestrian navigation), or No value (Information is Unknown).
RST_STAIRS_TRAVERSAL	Stairs Restriction	Identifies whether stairs should be avoided on a pedestrian suitable route: Y (Stairs should be avoided on a pedestrian suitable route), N (Stairs should not be avoided on a pedestrian suitable route), or No value (Information is Unknown).
Shape_Length *	Length of feature in internal units	Positive real numbers that are automatically generated.
CARTO	Carto	Cartographic field that may be used for street symbolization.
SHIELD_LABEL	Shield Label	Abridged shield number (used for labeling purposes to improve cartographic display): Characters for the features derived from the StreetNameBase fields. <b>Note:</b> Priority for selecting shield label from multiple alternative names is based on the level of route type and official language code for specified country.
SHIELD_CLASS	Shield Class	Classification for shields labeling.
LABEL_TYPE	Label Type	Used for displaying Routing_Streets feature class labels in ArcGIS Pro and Navigator. The default is for

Field Name	Description	Values
		custom streets feature labels to draw at all scales. If you don't want custom streets feature labels to draw at all scales, code the custom streets feature attributes based on the Routing_Streets features which they connect to for a similar cartographic effect.
LABEL_PRIORITY	Label Priority	Used for displaying Routing_Streets feature class labels in ArcGIS Pro and Navigator. The default is for custom streets feature labels to draw at all scales. If you don't want custom streets feature labels to draw at all scales, code the custom streets feature attributes based on the Routing_Streets features which they connect to for a similar cartographic effect.
FT_KPH	From KPH	Indicates the speed in kph in the From direction on the link.
TF_KPH	Toward KPH	Indicates the speed in kph in the Toward direction on the link.
FT_TRUCK_KPH	From Truck KPH	Indicates the speed in kph for trucks in the From direction on the link.
TF_TRUCK_KPH	Toward Truck KPH	Indicates the speed in kph for trucks in the Toward direction on the link.

\* The Shape\_Length field contains the projected planar distance in the Web Mercator coordinate system. The [Web Mercator projection](#) does not preserve distances well, so the Shape\_Length field is less usable as a distance measure. The Web Mercator projection distorts distances most in north-south directions but east-west directions as well with distance from the equator also a factor. For this reason, it is best to calculate (and keep updated due to any geometry edits) the geodesic distance in the METERS field.

## Custom Turn Restrictions (Custom\_Turns)

The Custom Turn Restrictions (Custom\_Turns File Geodatabase Feature Class) line layer is an empty feature class to contain restrictions to the network which are defined based on two or more links.

This layer contains the following fields:

Field Name	Description	Values
OBJECTID	Internal feature number	Sequential unique whole numbers that are automatically generated.

Field Name	Description	Values
Shape	Feature geometry	Coordinates defining the features.
Edge1End	Edge 1 End	Indicates if the second Edge connects at the From End or To End of the first Edge. Values: Y (Turn passes through the end of the first edge) or N (Turn passes through the beginning of the first edge).
Edge1FCID	Edge 1 Feature Class ID	The Feature Class ID corresponding to the first edge element in the turn restriction maneuver sequence.
Edge1FID	Edge 1 Feature ID	The Feature ID corresponding to the first edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge1Pos	Edge 1 Position	The position along the linear feature that represents the first edge element in the turn restriction maneuver sequence. This allows for the usage of streets composed of multiple edge elements.
Edge2FCID	Edge 2 Feature Class ID	The Feature Class ID corresponding to the second edge element in the turn restriction maneuver sequence.
Edge2FID	Edge 2 Feature ID	The Feature ID corresponding to the second edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge2Pos	Edge 2 Position	The position along the linear feature that represents the second edge element in the turn restriction maneuver sequence.
Edge3FCID	Edge 3 Feature Class ID	The Feature Class ID corresponding to the third edge element in the turn restriction maneuver sequence.
Edge3FID	Edge 3 Feature ID	The Feature ID corresponding to the third edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge3Pos	Edge 3 Position	The position along the linear feature that represents the third edge element

Field Name	Description	Values
		in the turn restriction maneuver sequence.
Edge4FCID	Edge 4 Feature Class ID	The Feature Class ID corresponding to the fourth edge element in the turn restriction maneuver sequence.
Edge4FID	Edge 4 Feature ID	The Feature ID corresponding to the fourth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge4Pos	Edge 4 Position	The position along the linear feature that represents the fourth edge element in the turn restriction maneuver sequence.
Edge5FCID	Edge 5 Feature Class ID	The Feature Class ID corresponding to the fifth edge element in the turn restriction maneuver sequence.
Edge5FID	Edge 5 Feature ID	The Feature ID corresponding to the fifth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge5Pos	Edge 5 Position	The position along the linear feature that represents the fifth edge element in the turn restriction maneuver sequence.
Edge6FCID	Edge 6 Feature Class ID	The Feature Class ID corresponding to the sixth edge element in the turn restriction maneuver sequence.
Edge6FID	Edge 6 Feature ID	The Feature ID corresponding to the sixth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge6Pos	Edge 6 Position	The position along the linear feature that represents the sixth edge element in the turn restriction maneuver sequence.
Edge7FCID	Edge 7 Feature Class ID	The Feature Class ID corresponding to the seventh edge element in the turn restriction maneuver sequence.
Edge7FID	Edge 7 Feature ID	The Feature ID corresponding to the seventh edge element in the turn

Field Name	Description	Values
		restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge7Pos	Edge 7 Position	The position along the linear feature that represents the seventh edge element in the turn restriction maneuver sequence.
Edge8FCID	Edge 8 Feature Class ID	The Feature Class ID corresponding to the eighth edge element in the turn restriction maneuver sequence.
Edge8FID	Edge 8 Feature ID	The Feature ID corresponding to the eighth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge8Pos	Edge 8 Position	The position along the linear feature that represents the eighth edge element in the turn restriction maneuver sequence.
Edge9FCID	Edge 9 Feature Class ID	The Feature Class ID corresponding to the ninth edge element in the turn restriction maneuver sequence.
Edge9FID	Edge 9 Feature ID	The Feature ID corresponding to the ninth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge9Pos	Edge 9 Position	The position along the linear feature that represents the ninth edge element in the turn restriction maneuver sequence.
Edge10FCID	Edge 10 Feature Class ID	The Feature Class ID corresponding to the tenth edge element in the turn restriction maneuver sequence.
Edge10FID	Edge 10 Feature ID	The Feature ID corresponding to the tenth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge10Pos	Edge 10 Position	The position along the linear feature that represents the tenth edge element

Field Name	Description	Values
		in the turn restriction maneuver sequence.
Edge11FCID	Edge 11 Feature Class ID	The Feature Class ID corresponding to the eleventh edge element in the turn restriction maneuver sequence.
Edge11FID	Edge 11 Feature ID	The Feature ID corresponding to the eleventh edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge11Pos	Edge 11 Position	The position along the linear feature that represents the eleventh edge element in the turn restriction maneuver sequence.
Edge12FCID	Edge 12 Feature Class ID	The Feature Class ID corresponding to the twelfth edge element in the turn restriction maneuver sequence.
Edge12FID	Edge 12 Feature ID	The Feature ID corresponding to the twelfth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge12Pos	Edge 12 Position	The position along the linear feature that represents the twelfth edge element in the turn restriction maneuver sequence.
Edge13FCID	Edge 13 Feature Class ID	The Feature Class ID corresponding to the thirteenth edge element in the turn restriction maneuver sequence.
Edge13FID	Edge 13 Feature ID	The Feature ID corresponding to the thirteenth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge13Pos	Edge 13 Position	The position along the linear feature that represents the thirteenth edge element in the turn restriction maneuver sequence.
Edge14FCID	Edge 14 Feature Class ID	The Feature Class ID corresponding to the fourteenth edge element in the turn restriction maneuver sequence.
Edge14FID	Edge 14 Feature ID	The Feature ID corresponding to the fourteenth edge element in the turn

Field Name	Description	Values
		restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge14Pos	Edge 14 Position	The position along the linear feature that represents the fourteenth edge element in the turn restriction maneuver sequence.
Edge15FCID	Edge 15 Feature Class ID	The Feature Class ID corresponding to the fifteenth edge element in the turn restriction maneuver sequence.
Edge15FID	Edge 15 Feature ID	The Feature ID corresponding to the fifteenth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge15Pos	Edge 15 Position	The position along the linear feature that represents the fifteenth edge element in the turn restriction maneuver sequence.
Edge16FCID	Edge 16 Feature Class ID	The Feature Class ID corresponding to the sixteenth edge element in the turn restriction maneuver sequence.
Edge16FID	Edge 16 Feature ID	The Feature ID corresponding to the sixteenth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge16Pos	Edge 16 Position	The position along the linear feature that represents the sixteenth edge element in the turn restriction maneuver sequence.
Edge17FCID	Edge 17 Feature Class ID	The Feature Class ID corresponding to the seventeenth edge element in the turn restriction maneuver sequence.
Edge17FID	Edge 17 Feature ID	The Feature ID corresponding to the seventeenth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge17Pos	Edge 17 Position	The position along the linear feature that represents the seventeenth edge

Field Name	Description	Values
		element in the turn restriction maneuver sequence.
Edge18FCID	Edge 18 Feature Class ID	The Feature Class ID corresponding to the eighteenth edge element in the turn restriction maneuver sequence.
Edge18FID	Edge 18 Feature ID	The Feature ID corresponding to the eighteenth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge18Pos	Edge 18 Position	The position along the linear feature that represents the eighteenth edge element in the turn restriction maneuver sequence.
Edge19FCID	Edge 19 Feature Class ID	The Feature Class ID corresponding to the nineteenth edge element in the turn restriction maneuver sequence.
Edge19FID	Edge 19 Feature ID	The Feature ID corresponding to the nineteenth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge19Pos	Edge 19 Position	The position along the linear feature that represents the nineteenth edge element in the turn restriction maneuver sequence.
Edge20FCID	Edge 20 Feature Class ID	The Feature Class ID corresponding to the twentieth edge element in the turn restriction maneuver sequence.
Edge20FID	Edge 20 Feature ID	The Feature ID corresponding to the twentieth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge20Pos	Edge 20 Position	The position along the linear feature that represents the twentieth edge element in the turn restriction maneuver sequence.
Edge21FCID	Edge 21 Feature Class ID	The Feature Class ID corresponding to the twenty-first edge element in the turn restriction maneuver sequence.
Edge21FID	Edge 21 Feature ID	The Feature ID corresponding to the twenty-first edge element in the turn

Field Name	Description	Values
		restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge21Pos	Edge 21 Position	The position along the linear feature that represents the twenty-first edge element in the turn restriction maneuver sequence.
Edge22FCID	Edge 22 Feature Class ID	The Feature Class ID corresponding to the twenty-second edge element in the turn restriction maneuver sequence.
Edge22FID	Edge 22 Feature ID	The Feature ID corresponding to the twenty-second edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge22Pos	Edge 22 Position	The position along the linear feature that represents the twenty-second edge element in the turn restriction maneuver sequence.
Edge23FCID	Edge 23 Feature Class ID	The Feature Class ID corresponding to the twenty-third edge element in the turn restriction maneuver sequence.
Edge23FID	Edge 23 Feature ID	The Feature ID corresponding to the twenty-third edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge23Pos	Edge 23 Position	The position along the linear feature that represents the twenty-third edge element in the turn restriction maneuver sequence.
Edge24FCID	Edge 24 Feature Class ID	The Feature Class ID corresponding to the twenty-fourth edge element in the turn restriction maneuver sequence.
Edge24FID	Edge 24 Feature ID	The Feature ID corresponding to the twenty-fourth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge24Pos	Edge 24 Position	The position along the linear feature that represents the twenty-fourth edge

Field Name	Description	Values
		element in the turn restriction maneuver sequence.
Edge25FCID	Edge 25 Feature Class ID	The Feature Class ID corresponding to the twenty-fifth edge element in the turn restriction maneuver sequence.
Edge25FID	Edge 25 Feature ID	The Feature ID corresponding to the twenty-fifth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge25Pos	Edge 25 Position	The position along the linear feature that represents the twenty-fifth edge element in the turn restriction maneuver sequence.
Edge26FCID	Edge 26 Feature Class ID	The Feature Class ID corresponding to the twenty-sixth edge element in the turn restriction maneuver sequence.
Edge26FID	Edge 26 Feature ID	The Feature ID corresponding to the twenty-sixth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge26Pos	Edge 26 Position	The position along the linear feature that represents the twenty-sixth edge element in the turn restriction maneuver sequence.
Edge27FCID	Edge 27 Feature Class ID	The Feature Class ID corresponding to the twenty-seventh edge element in the turn restriction maneuver sequence.
Edge27FID	Edge 27 Feature ID	The Feature ID corresponding to the twenty-seventh edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge27Pos	Edge 27 Position	The position along the linear feature that represents the twenty-seventh edge element in the turn restriction maneuver sequence.
Edge28FCID	Edge 28 Feature Class ID	The Feature Class ID corresponding to the twenty-eighth edge element in the turn restriction maneuver sequence.
Edge28FID	Edge 28 Feature ID	The Feature ID corresponding to the twenty-eighth edge element in the turn

Field Name	Description	Values
		restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge28Pos	Edge 28 Position	The position along the linear feature that represents the twenty-eighth edge element in the turn restriction maneuver sequence.
Edge29FCID	Edge 29 Feature Class ID	The Feature Class ID corresponding to the twenty-ninth edge element in the turn restriction maneuver sequence.
Edge29FID	Edge 29 Feature ID	The Feature ID corresponding to the twenty-ninth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge29Pos	Edge 29 Position	The position along the linear feature that represents the twenty-ninth edge element in the turn restriction maneuver sequence.
Edge30FCID	Edge 30 Feature Class ID	The Feature Class ID corresponding to the thirtieth edge element in the turn restriction maneuver sequence.
Edge30FID	Edge 30 Feature ID	The Feature ID corresponding to the thirtieth edge element in the turn restriction maneuver sequence. The Edge Feature ID is an Esri-specific ID and refers to the Object ID in the Routing_Streets layer.
Edge30Pos	Edge 30 Position	The position along the linear feature that represents the thirtieth edge element in the turn restriction maneuver sequence.
RST_AUTOMOBILES	Automobiles Restricted	Indicates if Automobiles are restricted from traversing the turn: Y (Applies) or N (Does not apply).
RST_BUSES	Buses Restricted	Indicates if Buses are restricted from traversing the turn: Y (Applies) or N (Does not apply).
RST_TAXIS	Taxis Restricted	Indicates if Taxis are restricted from traversing the turn: Y (Applies) or N (Does not apply).
RST_PEDESTRIANS	Pedestrians Restricted	Indicates if Pedestrians are restricted from traversing the turn: Y (Applies) or N (Does not apply).

Field Name	Description	Values
RST_TRUCK_DELIVERY_ONLY	Trucks Restricted (Except Local Deliveries)	Indicates maneuvers where Trucks are allowed only to make a Delivery in the local vicinity: Y (Applies) or N (Does not apply).
RST_THROUGH_TRAFFIC	Through Traffic Restricted	Indicates if Automobile Through Traffic is restricted from traversing the turn: Y (Applies) or N (Does not apply).
RST_TRUCKS	Trucks Restricted	Indicates maneuvers where Trucks are prohibited from travel at all times: Y (Applies) or N (Does not apply).
RST_EMERGENCY_VEHICLES	Emergency Vehicles Restricted	Indicates if Emergency Vehicles are restricted from traversing the turn: Y (Applies) or N (Does not apply).
RST_RESIDENTIAL_VEHICLES	Residential Vehicles Restricted	Indicates if Residential Vehicles are restricted from using the link: Y (Applies) or <Null> (Does not apply).
RST_MOTORCYCLES	Motorcycles Restricted	Indicates if Motorcycles are restricted from traversing the turn: Y (Applies) or N (Does not apply).
RST_GATE_KEY	Keyed Access Entryway	Identifies the presence of a gate requiring key access: Y (Applies) or N (Does not apply).
RST_GATE_PERMISSIONS	Guard Controlled Entryway	Identifies the presence of a guard controlled gate: Y (Applies) or N (Does not apply).
RST_HEIGHT	Height Restriction	Restricts vehicles exceeding a specific height in meters.
RST_WEIGHT	Weight Restriction	Restricts vehicles exceeding a specific weight in kilograms.
RST_WEIGHT_PER_AXLE	Weight per Axle Restriction	Restricts vehicles exceeding a specific weight per axle in kilograms.
RST_LENGTH	Length Restriction	Restricts vehicles exceeding a specific length in meters.
RST_WIDTH	Width Restriction	Restricts vehicles exceeding a specific width in meters.
RST_TRUCK_TRAILERS	Truck with Trailers Restriction	Specifies the occurrence of a restriction on a link or lane related to trucks with a specified number of trailers: <Null> (Restriction does not apply), 1 (Truck with one or more trailers is restricted), 2 (Truck with two or more trailers is restricted), or 3 (Truck with three or more trailers is restricted).

Field Name	Description	Values
RST_SEMI_TRACTOR_TRAILERS	Semi or Tractor with One or more Trailers Forbidden	Indicates a turn restriction for semi or tractor trucks with one or more trailers: Y (Applies) or N (Does not apply).
RST_HAZMAT_EXPLOSIVES	Hazmat: Explosives	Indicates a restriction for Hazardous Materials (Explosives): Y (Applies) or N (Does not apply).
RST_HAZMAT_GAS	Hazmat: Gas	Indicates a restriction for Hazardous Materials (Gas): Y (Applies) or N (Does not apply).
RST_HAZMAT_FLAMABLE_LIQUID	Hazmat: Flammable	Indicates a restriction for Hazardous Materials (Flammable): Y (Applies) or N (Does not apply).
RST_HAZMAT_FLAMABLE_SOLID	Hazmat: Flammable Solid or Combustible	Indicates a restriction for Hazardous Materials (Flammable Solid or Combustible): Y (Applies) or N (Does not apply).
RST_HAZMAT_ORGANIC	Hazmat: Organic	Indicates a restriction for Hazardous Materials (Organic): Y (Applies) or N (Does not apply).
RST_HAZMAT_POISON	Hazmat: Poison	Indicates a restriction for Hazardous Materials (Poison): Y (Applies) or N (Does not apply).
RST_HAZMAT_RADIOACTIVE	Hazmat: Radioactive	Indicates a restriction for Hazardous Materials (Radioactive): Y (Applies) or N (Does not apply).
RST_HAZMAT_CORROSIVE	Hazmat: Corrosive	Indicates a restriction for Hazardous Materials (Corrosive): Y (Applies) or N (Does not apply).
RST_HAZMAT_OTHER	Hazmat: Other	Indicates a restriction for Hazardous Materials (Other): Y (Applies) or N (Does not apply).
RST_ANY_HAZMAT_MATERIAL	All Hazmats	Indicates a restriction for All Hazardous Materials: Y (Applies) or N (Does not apply).
RST_HAZMAT_POISONOUS	Hazmat: Poisonous Inhalation Hazard	Indicates a restriction for Hazardous Materials (Poisonous Inhalation Hazard): Y (Applies) or N (Does not apply).
RST_GOODS_HARMFUL_WATER	Goods Harmful to Water	Indicates a restriction for All Trucks with Natural Goods that can be Harmful to Water: Y (Applies) or N (Does not apply).
RST_HAZMAT_EXPLOSIVES_FLAMABLE	Explosive and Flammable Goods	Indicates a restriction for All Trucks with Explosive and Flammable Goods: Y (Applies) or N (Does not apply).

Field Name	Description	Values
RST_AXLE_COUNT	Axle Count Restriction	Specifies the occurrence of a turn restriction related to trucks with a specified number of Axles: <Null> (Restriction does not apply), 1 (Two or more axles are restricted), 2 (Three or more axles are restricted), 3 (Four or more axles are restricted), 4 (Five or more axles are restricted), or 5 (Six or more axles are restricted).
RST_SINGLE_AXLE_VEHICLE	Single Axle Vehicles Prohibited	Indicates a turn restriction for Single Axle vehicles: Y (Applies) or N (Does not apply).
RST_TANDEM_AXLE_VEHICLE	Tandem Axle Vehicles Prohibited	Indicates a turn restriction for Tandem Axle Vehicles: Y (Applies) or N (Does not apply).
FEAT_ID	Feature Identification	Unique feature identifier for the street segment: Unique numbers for the features.
Shape_Length	Length of feature in internal units	Positive real numbers that are automatically generated.

## Reference

### Directional Identifiers

**Definition:** Directional identifier that precedes or follows the feature name. These identifiers can be added to the STREET\_PREFIX\_DIR or STREET\_DIR attributes in the Custom\_Roads feature class.

Value	Description			
	ENG	ARA	FRE	SPA
E	East	شرق	Est	Este
N	North	شمال	Nord	Norte
NE	Northeast	None	Nord-est	Nord-este
NO	None	None	Nord-ouest	Nor-oeste
NW	Northwest	None	None	None
O	None	None	Ouest	Oeste
S	South	جنوب	Sud	Sur
SE	Southeast	None	Sud-est	Sud-este
SO	None	None	Sud-ouest	Sud-oeste
SW	Southwest	None	None	None

Value	Description			
	ENG	ARA	FRE	SPA
W	West	غرب	None	None

## Direction on Sign

**Definition:** Official directional identifier assigned to the highway that is the official direction and not necessarily the travel direction. These identifiers can be added to the STREET\_NAME\_DIRECTION attribute in the Custom\_Roads feature class.

Code	Description
E	East (Language Code = 'ENG'), Est (Language Code = 'FRE'), Este (Language Code = 'SPA').
N	North (Language Code = 'ENG'), Nord (Language Code = 'FRE'), Norte (Language Code = 'SPA').
O	Ouest (Language Code = 'FRE'), Oeste (Language Code = 'SPA').
S	South (Language Code = 'ENG'), Sud (Language Code = 'FRE'), Sur (Language Code = 'SPA').
W	West (Language Code = 'ENG').
No value	Not applicable.

## Hierarchy

**Definition:** Defines a hierarchical network used to determine a logical and efficient route for a traveler. Hierarchy values relate to the routing classification of the road segment. The lower the hierarchy value, the more important the street segment is in the routing hierarchy, such as interstates or roads of international importance. The routing classification is not maintained as a separate attribute.

During hierarchical analyses, if you want the solver to analyze your Custom\_Streets in a similar manner to Routing\_Streets, follow the example below by adding the codes to the HIERARCHY attribute in the Custom\_Streets feature class. It is important not to break hierarchy classes, for example do not create a road with Hierarchy = 2 connecting two roads having Hierarchy = 1. For more information, read the [hierarchy help documentation](#).

HIERARCHY	Routing classification
1	Road of International Importance
2	Road of National Importance
3	Road of Regional Importance
4	Local Road of High Importance

HIERARCHY	Routing classification
5	Local or Restricted Road

## Maneuver Class Codes

The MANEUVER\_CLASS attribute identifies to the driving directions small connecting roads inside of or adjacent to the street intersection. It is a descriptor attribute of type integer whose values are shown in the following table. Plural Junction is not maintained as a separate attribute. Add these codes to the MANEUVER\_CLASS attribute in the Custom\_Streets feature class. The MANEUVER\_CLASS field is created using the following logic:

MANEUVER_CLASS	Maneuver Class Description	PJ	Plural Junction Description
0	Standard Road	0	Not part of Plural Junction (default)
		2	Indescribable
1	Intersection Internal	1	Intersection Internal
2	Maneuver Road	3	Maneuver

## Road Classes

The Road Class attribute provides specific directions for different types of roads. It is a descriptor attribute of type integer. If you want the driving directions text for your custom streets to be formatted similarly to that of Routing\_Streets, follow the example below by adding these codes to the ROAD\_CLASS attribute:

Road Class Value	Type of Road Class	Example Directions Text
1	Surface street	Turn left on Main St.
2	Highway	Go east on I-55.
3	Highway Ramp	Take ramp and go on US-59 N.
4	Ferry Crossing	Take Lake Expy ferry.
5	Roundabout	Take roundabout and proceed south on Main St.
6	Major road	Continue east on Central Ave.

## Speed Categories

The speed category classifies the general speed trend of a road based on posted or legal speed and is provided to enhance route calculation and the timing of route guidance. Speed category values represent the combination of several factors besides legal speed limit (for example, physical restrictions or access characteristics). Therefore, speed category values can differ from speed limit values, which represent the legal speed limit only. These speed categories are used to assign speed classes in the SPEED\_CLASS attribute.

SPEED_CATEGORY	Kilometers per hour (kph)	Miles per hour (mph)
No value	Not Applicable	Not Applicable
1	More than 130 kph	More than 80 mph
2	101–130 kph	65–80 mph
3	91–100 kph	55–64 mph
4	71–90 kph	41–54 mph
5	51–70 kph	31–40 mph
6	31–50 kph	21–30 mph
7	11–30 kph	6–20 mph
8	Less than 11 kph	Less than 6 mph

## Speed Classes

**Definition:** Speed Class (SPEED\_CLASS) is a combination of speed category, freeway classification, and road form. See [Speed Categories](#) (SPEED\_CATEGORY) for details about speed categories. The Freeway classification is whether a road segment represents a freeway (Yes or No). The Freeway classification is not maintained as a separate attribute.

Form of Way (ROAD\_FORM) indicates whether the road is a local road that runs parallel to a road with a higher traffic flow. The Form of Way (ROAD\_FORM) attribute is not maintained as a separate attribute in Routing\_Streets or Custom\_Streets.

Add the Speed Class codes to the SPEED\_CLASS attribute in the Custom\_Streets feature class.

SPEED_CLASS	SPEED_CATEGORY	Freeway	ROAD_FORM
1	1	Yes	<>6 OR <Null>
2	2	Yes	<>6 OR <Null>
3	3	Yes	<>6 OR <Null>
4	4	Yes	<>6 OR <Null>
5	5	Yes	<>6 OR <Null>
6	6	Yes	<>6 OR <Null>
7	7	Yes	<>6 OR <Null>

<b>SPEED_CLASS</b>	<b>SPEED_CATEGORY</b>	<b>Freeway</b>	<b>ROAD_FORM</b>
8	8	Yes	<>6 OR <Null>
9	1	No	<>6 OR <Null>
10	2	No	<>6 OR <Null>
11	3	No	<>6 OR <Null>
12	4	No	<>6 OR <Null>
13	5	No	<>6 OR <Null>
14	6	No	<>6 OR <Null>
15	7	No	<>6 OR <Null>
16	8	No	<>6 OR <Null>
17	1		6
18	2		6
19	3		6
21	5		6
22	6		6
23	7		6
24	8		6

## **Contents**

The ArcGIS StreetMap Premium Custom Roads project file (.aprx) contains both maps and basemaps as well as the following content.

<b>Map or Basemap Name</b>	<b>Map or Basemap Layers</b>		
Add Custom Streets map	World Imagery	Custom network layers	Network dataset
Navigation Day with Custom Streets (vtpk) map	Navigation vector tile package	Custom Streets	Network dataset
Navigation Day with Custom Streets (vtpk) basemap	Navigation vector tile package	Custom Streets	Network dataset
Navigation Dark with Custom Streets (vtpk) map	Navigation vector tile package	Custom Streets	Network dataset
Navigation Dark with Custom Streets (vtpk) basemap	Navigation vector tile package	Custom Streets	Network dataset

Maps and basemaps are distinguished by different icons in the ArcGIS Pro Contents Pane. The ArcGIS Pro project file (.aprx) includes basemaps created from the Custom Roads maps in case a basemap from ArcGIS Online is purposefully or accidentally added to one of the Custom Roads maps, in effect removing the Custom Roads map from the project. You may add the Custom Roads basemap back in from the list of basemaps or close the .aprx file without saving.

The following table details the data that is shipped with ArcGIS StreetMap Premium Custom Roads as well as whether the ArcGIS StreetMap Premium extension is required to use each component.

<b>ArcGIS StreetMap Premium Custom Roads product component</b>	<b>ArcGIS Pro</b>	<b>ArcGIS Enterprise (ArcGIS Server)</b>	<b>ArcGIS Navigator</b>
Editable file geodatabase (.gdb) for routing	StreetMap Premium extension*	StreetMap Premium extension*	Not applicable
Vector tile package (.vtpk) for mapping	Not applicable	Not applicable	Not applicable
Locators	StreetMap Premium extension*	StreetMap Premium extension*	Not applicable
Mobile map packages (.mmpk)**	StreetMap Premium extension*	StreetMap Premium extension*	StreetMap Premium extension*

\*Refer to ArcGIS Pro help for instructions on [enabling a StreetMap Premium extension](#) for ArcGIS Pro or ArcGIS Enterprise.

\*\*The StreetMap Premium extension is required for any mobile map package created from the ArcGIS StreetMap Premium Custom Roads dataset and opened in ArcGIS Pro.